

목차

RHEV Self-Hosted Backup/Restore	3
--	----------

RHEV Self-Hosted Backup/Restore

— 이강우 2017/02/15 19:07

본 문서는 작성중입니다.

Self hosted engine 복구 방법

- 단독형 Self-Hosted 구성에서도 복구 가능 (Self-Hosted host 1대인 경우)
- RHEV-M Backup Data만 있으면 복구 가능
- 동일 서버에 복구 가능

0. Global Maintenance mode (상관 없음, 장애시의 경우도 고려)

1. rhvm backup

```
engine-backup --scope=all --mode=backup --file=BACKUP_FILE --log=LOG_FILE
```

2. hosted-engine shutdown

```
hosted-engine --vm-shutdown
```

3. host 재설치

2. 새로운 selfhost 설치 (여기서부터 RHEVM VM에서 수행)

3. rhvm VM 설치 및 OS update

4. install rhvm

5. engine-setup

6. service ovirt-engine stop

7. engine-cleanup

8. restore db

```
su - postgres -c psql
```

```
alter role engine encrypted password 'PASSWORD';
```

```
engine-backup --mode=restore --scope=all --file=rhev3.6.backup --log=restore.log --change-db-credentials --db-host=localhost --db-name=engine --db-user=engine --db-password --restore-permissions
```

9. engine-setup

10. delete hosted_engine VM from db

```
delete from snapshots where snapshot_id=(select snapshot_id from snapshots where vm_id=(select vm_guid from vm_static where vm_name like 'HostedEngine'))
```

```
delete from vm_static where vm_guid=(select vm_guid from vm_static where vm_name like 'HostedEngine')
```

11. manager UI에서 hosted_engine host 리부팅 확인 -> 유지보수 -> 제거

12. selfhost 에서 종료

From:

<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:

https://atl.kr/dokuwiki/doku.php/rhev_self-hosted_backup_restore

Last update: **2017/02/16 06:40**

