

목차

**B120i 드라이버 설치 방법** ..... 3

*드라이버파일* ..... 3

*참조링크* ..... 4



# B120i 드라이버 설치 방법

출처 : <https://x1fingers.asuscomm.com/wordpress/gen8-esxi-disk-performance-issue/>

```
# 유지보수 모드로 전환, 화면에서 호스트->작업->유지보수 모드 시작과 동일
$ esxcli system maintenanceMode set -e true

# 외부 파일을 받을 수 있도록 방화벽을 일시 해제합니다.
$ esxcli network firewall ruleset set -e true -r httpClient

# tmp 디렉토리로 이동
$ cd /tmp

# 교체할 드라이버 다운로드
$ wget
http://downloads.hpe.com/pub/softlib2/software1/pubsw-linux/p1749737361/v987
67/hpvsa-5.5.0-88.zip

# 압축해제
$ unzip hpvsa-5.5.0-88.zip

# 파일복사
$ cp scsi-hpvsa-5.5.0-880EM.550.0.0.1331820.x86_64.vib /var/log/vmware/

# 기존 드라이버 삭제
$ esxcli software vib remove -n scsi-hpvsa -f

# 새로운 드라이버로 설치 (시간이 조금 걸릴 수 있습니다)
$ esxcli software vib install -v file:scsi-
hpvsa-5.5.0-880EM.550.0.0.1331820.x86_64.vib --force --no-sig-check --
maintenance-mode

# 상태 복원 및 ESXi 재기동
$ esxcli network firewall ruleset set -e false -r httpClient
$ esxcli system maintenanceMode set --enable false
$ esxcli system module set --enabled=false --module=vmw_ahci
$ reboot
```

## 드라이버파일

- hpvsa-5.5.0-88.zip
- scsi-hpvsa-5.5.0.102-1oem.550.0.0.1331820.x86\_64.zip
- scsi-hpvsa-5.5.0.108-1oem.550.0.0.1331820.x86\_64.zip

## 참조링크

- [https://support.hpe.com/hpesc/public/km/product/5293150/Product#t=DriversandSoftware&sort=%40kmswtypesort\\_ko%20ascending&f:@kmswsoftwaretypekey=\[swt8000113\]&f:@kmswtargetproductbaseenvironmentlatest=\[5293150\\_VMware\]](https://support.hpe.com/hpesc/public/km/product/5293150/Product#t=DriversandSoftware&sort=%40kmswtypesort_ko%20ascending&f:@kmswsoftwaretypekey=[swt8000113]&f:@kmswtargetproductbaseenvironmentlatest=[5293150_VMware])

From:  
<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:  
[https://atl.kr/dokuwiki/doku.php/b120i\\_%EB%93%9C%EB%9D%BC%EC%9D%B4%EB%B2%84\\_%EA%B4%80%EB%A0%A8\\_%EC%84%A4%EC%B9%98\\_%EB%B0%A9%EB%B2%95](https://atl.kr/dokuwiki/doku.php/b120i_%EB%93%9C%EB%9D%BC%EC%9D%B4%EB%B2%84_%EA%B4%80%EB%A0%A8_%EC%84%A4%EC%B9%98_%EB%B0%A9%EB%B2%95)

Last update: 2019/09/28 17:24

