

목차

RHEV 3.6 hosted-engine gateway 변경 3

작업 절차 3

 Put the cluster in global maintenance. 3

 Stop the HA services on all hosts: 3

 hosted-engine 저장볼륨의 설정파일 가져오기 3

 설정파일 재구성 3

 Start the HA services on all hosts: 4

 Disable global Maintenance: 4

참조 4

RHEV 3.6 hosted-engine gateway 변경

적용 버전 : RHEV 3.6 이후버전

아래 예제는 기본 gateway변경에 대한 내용만 있지만 그외에도 클러스터 이름 변경이나 다른 속성변경 시에도 응용할 수 있다.

작업 절차

Put the cluster in global maintenance.

```
# hosted-engine --set-maintenance --mode=global
```

Stop the HA services on all hosts:

```
# systemctl stop ovirt-ha-agent.service  
# systemctl stop ovirt-ha-broker.service
```

hosted-engine 저장볼륨의 설정파일 가져오기

```
# dir=`mktemp -d` && cd $dir  
# sdUUID_line=$(grep sdUUID /etc/ovirt-hosted-engine/hosted-engine.conf)  
# sdUUID=${sdUUID_line:7:36}  
# conf_volume_UUID_line=$(grep conf_volume_UUID /etc/ovirt-hosted-engine/hosted-engine.conf)  
# conf_volume_UUID=${conf_volume_UUID_line:17:36}  
# conf_image_UUID_line=$(grep conf_image_UUID /etc/ovirt-hosted-engine/hosted-engine.conf)  
# conf_image_UUID=${conf_image_UUID_line:16:36}  
# dd if=/rhev/data-center/mnt/blockSD/$sdUUID/images/$conf_image_UUID/$conf_volume_UUID  
2>/dev/null | tar -xvf -
```

여기까지 진행하면 hosted-engine 저장볼륨의 설정파일을 가져와 압축을 풀어놓게 된다.
필요한경우 fhanswers.conf 파일의 내용을 수정하거나 아래처럼 기존 answers 파일을 복사하도록 한다.

```
# cp /etc/ovirt-hosted-engine/answers.conf.rpmsave fhanswers.conf # or edit  
answers.conf as you need.
```

설정파일 재구성

수정 완료후 다시 설정파일을 압축하여 구성한다.

```
# tar -c0 * | dd of=/rhev/data-center/mnt/blockSD/$sdUUID/images/$conf_image_UUID/$conf_volume_UUID
```

Start the HA services on all hosts:

```
# systemctl start ovirt-ha-broker.service  
# systemctl start ovirt-ha-agent.service
```

Disable global Maintenance:

```
# hosted-engine --set-maintenance --mode=none
```

참조

- <https://access.redhat.com/solutions/2348341>

From:
<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:
https://atl.kr/dokuwiki/doku.php/rhev_3.6_hosted-engine_gateway_%EB%B3%80%EA%B2%BD

Last update: 2019/09/05 06:12

