

목차

Podman container storage경로 변경 3

Podman **설정파일 변경** 3

SELinux 를 사용하는경우 3

참조링크 3

Podman container storage 경로 변경

Podman 설정파일 변경

SELinux가 비활성화 되어있는 경우 단순히 /etc/containers/storage.conf 에서 경로만 변경해 주면 됩니다.

기본값은 아래와 같습니다. 해당 /var/lib/containers/storage 경로를 변경하고자 한다면

```
# Primary Read/Write location of container storage
graphroot = "/var/lib/containers/storage"
```

아래와 같이 /mnt/mystorage/virtual/storage 경로로 변경합니다.

```
# Primary Read/Write location of container storage
graphroot = "/mnt/mystorage/virtual/storage"
```

설정 내용을 확인합니다.

```
[root@lsrv1 mystorage]# podman info
```

SELinux 를 사용하는 경우

SELinux를 사용하는 경우 해당 경로에 SELinux Tagging을 진행해야 합니다.

```
[root@lsrv1 mystorage]# semanage fcontext -a -e /var/lib/containers
/mnt/mystorage/virtual/storage
[root@lsrv1 mystorage]# restorecon -Rv /mnt/mystorage/virtual/storage
restorecon reset /mnt/mystorage/virtual/storage context
unconfined_u:object_r:mnt_t:s0->unconfined_u:object_r:container_var_lib_t:s0
```

참조링크

- <https://ahelpme.com/software/podman/change-the-location-of-container-storage-in-podman-with-selinux-enabled/>

Last
update: podman_container_storage https://atl.kr/dokuwiki/doku.php/podman_container_storage%EA%B2%BD%EB%A1%9C_%EB%B3%80%EA%B2%BD
2023/12/18 경로_변경
06:51

From:
<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:
https://atl.kr/dokuwiki/doku.php/podman_container_storage%EA%B2%BD%EB%A1%9C_%EB%B3%80%EA%B2%BD

Last update: **2023/12/18 06:51**

