

목차

Rocky Linux

설치 / 구성

Rocky Linux Repository

.....

.....

.....

3

3

3

Rocky Linux

- CentOS에서 Rocky로 마이그레이션 <https://docs.rockylinux.org/guides/migrate2rocky/>
- Rocky Linux Instructional Books <https://docs.rockylinux.org/id/books/>

설치 / 구성

- 릴리즈 버전 고정 [release lock](#)

Rocky Linux Repository

Rocky Linux는 설치를 하게 되면 기본적으로 아래의 3개 레포지토리가 활성화 된다.

- BaseOS
- AppStream
- Extras

레포지토리는 이것 외에도 여러가지가 있다.

```
[root@rocky9-repo ~]# dnf repolist all
repo id                repo name
status
appstream              Rocky Linux 9 - AppStream
enabled
appstream-debuginfo   Rocky Linux 9 - AppStream - Debug
disabled
appstream-source      Rocky Linux 9 - AppStream - Source
disabled
baseos                 Rocky Linux 9 - BaseOS
enabled
baseos-debuginfo      Rocky Linux 9 - BaseOS - Debug
disabled
baseos-source         Rocky Linux 9 - BaseOS - Source
disabled
crb                   Rocky Linux 9 - CRB
disabled
crb-debuginfo         Rocky Linux 9 - CRB - Debug
disabled
crb-source            Rocky Linux 9 - CRB - Source
disabled
devel                 Rocky Linux 9 - Devel WARNING! FOR BUILDROOT
disabled
devel-debuginfo       Rocky Linux 9 - Devel Debug WARNING! FOR BUI
disabled
devel-source          Rocky Linux 9 - Devel Source WARNING! FOR BU
```

disabled	
extras	Rocky Linux 9 - Extras
enabled	
extras-debuginfo	Rocky Linux 9 - Extras Debug
disabled	
extras-source	Rocky Linux 9 - Extras Source
disabled	
highavailability	Rocky Linux 9 - High Availability
disabled	
highavailability-debuginfo	Rocky Linux 9 - High Availability - Debug
disabled	
highavailability-source	Rocky Linux 9 - High Availability - Source
disabled	
nfv	Rocky Linux 9 - NFV
disabled	
nfv-debuginfo	Rocky Linux 9 - NFV Debug
disabled	
nfv-source	Rocky Linux 9 - NFV Source
disabled	
plus	Rocky Linux 9 - Plus
disabled	
plus-debuginfo	Rocky Linux 9 - Plus - Debug
disabled	
plus-source	Rocky Linux 9 - Plus - Source
disabled	
resilientstorage	Rocky Linux 9 - Resilient Storage
disabled	
resilientstorage-debuginfo	Rocky Linux 9 - Resilient Storage - Debug
disabled	
resilientstorage-source	Rocky Linux 9 - Resilient Storage - Source
disabled	
rt	Rocky Linux 9 - Realtime
disabled	
rt-debuginfo	Rocky Linux 9 - Realtime Debug
disabled	
rt-source	Rocky Linux 9 - Realtime Source
disabled	
sap	Rocky Linux 9 - SAP
disabled	
sap-debuginfo	Rocky Linux 9 - SAP Debug
disabled	
sap-source	Rocky Linux 9 - SAP Source
disabled	
saphana	Rocky Linux 9 - SAPHANA
disabled	
saphana-debuginfo	Rocky Linux 9 - SAPHANA Debug
disabled	
saphana-source	Rocky Linux 9 - SAPHANA Source
disabled	

위와 같은 레포지토리 목록을 확인할 수 있으며 Disabled 된 레포지토리는 `dnf config-manager -set-enable <REPO>` 명령어로 활성화 할 수 있다.

```
[root@rocky9-repo]# dnf config-manager --set-enable highavailability plus
[root@rocky9-repo ~]# dnf repolist all
repo id                repo name
status
appstream              Rocky Linux 9 - AppStream
enabled
appstream-debuginfo   Rocky Linux 9 - AppStream - Debug
disabled
appstream-source      Rocky Linux 9 - AppStream - Source
disabled
baseos                 Rocky Linux 9 - BaseOS
enabled
baseos-debuginfo      Rocky Linux 9 - BaseOS - Debug
disabled
baseos-source         Rocky Linux 9 - BaseOS - Source
disabled
crb                   Rocky Linux 9 - CRB
disabled
crb-debuginfo         Rocky Linux 9 - CRB - Debug
disabled
crb-source            Rocky Linux 9 - CRB - Source
disabled
devel                 Rocky Linux 9 - Devel WARNING! FOR BUILDROOT
disabled
devel-debuginfo       Rocky Linux 9 - Devel Debug WARNING! FOR BUI
disabled
devel-source          Rocky Linux 9 - Devel Source WARNING! FOR BU
disabled
extras                Rocky Linux 9 - Extras
enabled
extras-debuginfo      Rocky Linux 9 - Extras Debug
disabled
extras-source         Rocky Linux 9 - Extras Source
disabled
highavailability      Rocky Linux 9 - High Availability
enabled
highavailability-debuginfo Rocky Linux 9 - High Availability - Debug
disabled
highavailability-source Rocky Linux 9 - High Availability - Source
disabled
nfv                   Rocky Linux 9 - NFV
disabled
nfv-debuginfo         Rocky Linux 9 - NFV Debug
disabled
nfv-source            Rocky Linux 9 - NFV Source
disabled
plus                  Rocky Linux 9 - Plus
```

enabled	
plus-debuginfo	Rocky Linux 9 - Plus - Debug
disabled	
plus-source	Rocky Linux 9 - Plus - Source
disabled	
resilientstorage	Rocky Linux 9 - Resilient Storage
disabled	
resilientstorage-debuginfo	Rocky Linux 9 - Resilient Storage - Debug
disabled	
resilientstorage-source	Rocky Linux 9 - Resilient Storage - Source
disabled	
rt	Rocky Linux 9 - Realtime
disabled	
rt-debuginfo	Rocky Linux 9 - Realtime Debug
disabled	
rt-source	Rocky Linux 9 - Realtime Source
disabled	
sap	Rocky Linux 9 - SAP
disabled	
sap-debuginfo	Rocky Linux 9 - SAP Debug
disabled	
sap-source	Rocky Linux 9 - SAP Source
disabled	
saphana	Rocky Linux 9 - SAPHANA
disabled	
saphana-debuginfo	Rocky Linux 9 - SAPHANA Debug
disabled	
saphana-source	Rocky Linux 9 - SAPHANA Source
disabled	

다시 비활성화 하려면 `dnf config-manager --set-disable highavailability plus` 와 같이 사용할 수 있다.

From:

<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:

https://atl.kr/dokuwiki/doku.php/rocky_linux

Last update: **2025/06/09 08:05**

