

목차

GlusterFS - Commands

Volume

Peer

.....

.....

.....

3

3

4

GlusterFS - Commands

참조문서 : <http://itscom.org/archives/4573>

Volume

```
[root@localhost ~] # gluster
```

볼륨 정보 □ volume info all □ volume info 볼륨명

```
gluster> volume info V_dist
```

볼륨 생성 □ volume create 볼륨명 [stripe <count> [transport <tcp>] <NEW-BRICK>

```
gluster> volume create V_stripe stripe 2 transport tcp gstor1:/data/st1  
gstor2:/data/st1
```

볼륨 삭제 □ volume delete 볼륨명 (볼륨이 시작된 경우 volume stop 볼륨명 먼저실행)

```
gluster> volume delete V_replica
```

볼륨 시작 □ volume start 볼륨명 [force]

```
gluster> volume start V_dist
```

볼륨 중지 □ volume stop 볼륨명 [force]

```
gluster> volume stop V_dist
```

브릭 추가 □ volume add-brick 볼륨명 [<stript|replica> <count>] <NEW-BRICK> [force]

```
gluster> volume add-brick V_dist gstor1:/data/dist3
```

브릭 제거 □ volume remove-brick 볼륨명 [replica <count>] 브릭 [start|stop|status|commit|force]

```
gluster> volume remove-brick V_dist gstor1:/data/dist3 force
```

볼륨 균형 □ volume rebalance 볼륨명 [fix-layout] {start|stop|status} [force]

```
gluster> volume rebalance V_dist start
```

브릭 교체 □ volume replace-brick 볼륨명 <BRICK> <NEW-BRICK> {start [force]|pause|abort|status|commit [force]}

```
gluster> volume replace-brick V_dist gstor1:/data/dist gstor1:/data/dist1  
start
```

```
gluster> volume replace-brick V_dist gstor1:/data/dist gstor1:/data/dist1  
status
```

```
gluster> volume replace-brick V_dist gstor1:/data/dist gstor1:/data/dist1  
commit force
```

볼륨 셋팅 □ volume set 볼륨명 <KEY> <VALUE>

```
gluster> volume set
```

볼륨 싱크 □ volume sync <호스트명> [all|볼륨명]
gluster> volume sync

볼륨 리셋 □ volume reset 볼륨명 [옵션] [force]
gluster> volume reset V_dist

볼륨 프로파일 □ volume profile 볼륨명 {start|stop|info [nfs]}
gluster> volume profile V_dist start
gluster> volume profile V_dist info

볼륨 쿼터 □ volume quota 볼륨명 {enable|disable|list [<path> ...]|remove
<path>| default-soft-limit <percent>}
먼저 mkdir /var/run/gluster 합니다.
gluster> volume quota V_dist enable

볼륨 쿼터 □ volume quota 볼륨명 {limit-usage <path> <size> [<percent>]}
gluster> volume quota V_dist limit-usage

볼륨 쿼터 □ volume quota 볼륨명 {alert-time|soft-timeout|hard-timeout}
{<time>}
#

볼륨 top □ volume top 볼륨명 {open|read|write|opendir|readdir|clear}
[nfs|brick <brick>] [list-cnt <value>]
gluster> volume top V_dist open

볼륨 top □ volume top 볼륨명 {read-perf|write-perf} [bs <size> count <count>]
[brick <brick>] [list-cnt <value>]

볼륨 상태 □ volume status [all | <VOLNAME> [nfs|shd|<BRICK>|quotad]]
[detail|clients|mem|inode|fd|callpool|tasks]
gluster> volume status all

Peer

[root@localhost ~]# gluster
스토리지 추가 □ peer probe 호스트명
peer probe gstor1

스토리지 제거 □ peer detach 호스트명
gluster> peer detach gstor1 force

연결상태 □ peer status
gluster> peer status

From:

<https://atl.kr/dokuwiki/> - **AllThatLinux!**

Permanent link:

https://atl.kr/dokuwiki/doku.php/glusterfs_-_commands

Last update: **2015/07/29 08:37**

