

목차

Openstack overcloud 설치 시 에러메세지 확인	3
--	----------

Openstack overcloud 설치 시 에러메세지 확인

오버클라우드 설치 시 에러와 함께 설치가 되지 않은 경우 아래 명령어로 에러메세지 상세 조회가 가능하다.

```
# openstack stack failures list overcloud --long
```

오버클라우드 실패 원인 찾기 접근 방법 #2

```
# heat resource-show overcloud Controller
resource_status CREATE_FAILED 상태 확인 혹은 아래 명령어로 실패 확인
# openstack stack resource list overcloud -c resource_name -c
resource_status | grep 'CREATE_FAILED'
```

```
#heat resource-list -n5 overcloud|grep -v COMPLE
```

resource_name	physical_resource_id	resource_status	updated_time
Controller	684e08e4-a304-4630-90fe-c9c24c3b45a7	CREATE_FAILED	2019-12-12T09:25:09Z
OS::Heat::ResourceGroup			
overcloud			
0	2735e632-d8dd-4baa-9981-937cd1ac489f	CREATE_FAILED	2019-12-12T09:28:25Z
OS::Triple0::Controller			
overcloud-Controller-65ojpltgs3jd			
NetworkDeployment	d6d8cab5-47a1-4020-bd63-431c3cc41d83	CREATE_FAILED	2019-12-12T09:28:27Z
OS::Triple0::SoftwareDeployment			
overcloud-Controller-65ojpltgs3jd-0-fzjjcdw7sghj			

```
# echo -e `heat deployment-show [physical_resource_id]
WARNING (shell) "heat deployment-show" is deprecated, please use "openstack
software deployment show" instead
{ "status": "FAILED", "server_id": "8e912488-5e86-4db2-8c2a-2fe00b21e7eb",
"config_id": "342e9b47-39ab-48af-8743-aab783e8b508", "output_values": {
"deploy_stdout": "Device has generated MAC, skipping.
Device has generated MAC, skipping.
ERROR: configuration of safe defaults failed.
```

위와 같이 상세 로그를 볼 수 있음

From: <https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link: https://atl.kr/dokuwiki/doku.php/openstack_overcloud_%EC%84%A4%EC%B9%98_%EC%8B%9C_%EC%97%90%EB%9F%AC%EB%A9%94%EC%84%B8%EC%A7%80_%ED%99%95%EC%9D%B8

Last update: 2020/04/22 04:13

