

목차

RHEV Hot Swap / Hot Plug Support 3

RHEV 버전별 지원 사항 3

 참조링크 3

Guest OS 요구사항 3

 참고링크 3

 주의사항 3

oVirt 지원 표 4

 참고링크 4

RHEV Hot Swap / Hot Plug Support

RHEV 버전별 지원 사항

RHEV 버전	지원사항
RHEV 3.1	Virtual Disk Hot-Plug
RHEV 3.4	Virtual Cpu Hot-Plug
RHEV 3.6	Virtual Memory Hot-plug (base RHEL7 Hypervisor)

참조링크

- <https://access.redhat.com/solutions/286813>

Guest OS 요구사항

OS	Version	Architecture	Hot Plug Supported
RHEL 6.3+		x86	Yes
RHEL 7.0+		x86	Yes
Windows Server 2003	All	All	No
Windows Server 2008	All	x86	No
Windows Server 2008	Standard, Enterprise	x64	No
Windows Server 2008	Datacenter	x64	Yes
Windows Server 2008 R2	All	x86	No
Windows Server 2008 R2	Standard, Enterprise	x64	No
Windows Server 2008 R2	Datacenter	x64	Yes
Windows Server 2012	All	x64	Yes
Windows Server 2012 R2	All	x64	Yes
Windows 7	All	x86	No
Windows 7	Starter, Home, Pro	x64	No
Windows 7	Enterprise, Ultimate	x64	Yes
Windows 8.x	All	x86	Yes
Windows 8.x	All	x64	Yes

참고링크

- <https://access.redhat.com/articles/1339413>
- <https://access.redhat.com/solutions/484933>
- <https://access.redhat.com/solutions/144343>
- <https://access.redhat.com/solutions/351923>

주의사항

- <https://access.redhat.com/solutions/351923> 에 따르면 RHEV 3.4 버전까지는 vCPU Hot-plug는 가

능하지만 Hot-unplug는 아직 제공하지 않는다고 되어있음

oVirt 지원 표

아래는 오픈소스 버전 oVirt 기준 Guest OS Hot Plug 지원 테이블임

OS	Version	Arch	Plug	Unplug
Red Hat Enterprise Linux 6.3		x86	+	-
Red Hat Enterprise Linux 6.5		x86	+	+
Microsoft Windows Server 2003	All	x86	-	-
Microsoft Windows Server 2003	All	x64	-	-
Microsoft Windows Server 2008	All	x86	-	-
Microsoft Windows Server 2008	Standard, Enterprise	x64	Reboot Required	Reboot Required
Microsoft Windows Server 2008	Datacenter	x64	+	?
Microsoft Windows Server 2008 R2	All	x86	-	-
Microsoft Windows Server 2008 R2	Standard, Enterprise	x64	Reboot Required	Reboot Required
Microsoft Windows Server 2008 R2	Datacenter	x64	+	?
Microsoft Windows Server 2012	All	x64	+	?
Microsoft Windows Server 2012 R2	All	x64	+	?
Microsoft Windows 7	All	x86	-	-
Microsoft Windows 7	Starter, Home, Home Premium, Professional	x64	Reboot Required	Reboot Required
Microsoft Windows 7	Enterprise, Ultimate	x64	+	?
Microsoft Windows 8.x	All	x86	+	?
Microsoft Windows 8.x	All	x64	+	?

참고링크

- <http://www.ovirt.org/develop/release-management/features/virt/hot-plug-cpu/>
- <http://www.ovirt.org/develop/release-management/features/hot-plug-memory/>
- <http://www.ovirt.org/develop/release-management/features/sla/memory-hotplug/>
- <http://www.ovirt.org/develop/release-management/features/storage/hotplug/>
- <http://www.ovirt.org/develop/release-management/features/storage/detailedhotplug/>
- <http://www.ovirt.org/develop/release-management/features/network/hotplugnic/>

From:

<https://atl.kr/dokuwiki/> - AllThatLinux!

Permanent link:

https://atl.kr/dokuwiki/doku.php/rhev_hot_swap_hot_plug_support

Last update: **2016/06/03 02:27**

